


Upgrading *INTELLISPEC* Software


You must be an Administrator to upgrade the system.

1. Download the upgrade file from www.presscosupport.com.
2. Unzip the file to a temporary directory on your PC and burn a CD with all the unzipped files.



All the files shown in the right panel above should be burned onto a CD.
 Important: Burn the CD with the contents in the root directory.

3. Take the CD to the Intellispec to be upgraded. Make sure the Intellispec is operating, and offline. Log in as Administrator or higher.



4. Click the Miscellaneous toolbar button
5. Select the Utilities tab
6. Click the Software Upgrade button
7. Insert the upgrade CD and click the Yes button to start the Setup program.
8. Click the Next button and follow the prompts as the upgrade proceeds.
9. Near the end of the upgrade process, there may be two rather serious-looking messages mentioning logo verification. Click the Continue Anyway button.
10. When the reboot prompt appears, click OK to restart but *do not remove the CD* until Windows shuts down.
11. The system will restart and run with the new version of software.

Some software upgrades require updating your software license key.
 If your upgrade won't run for this or any other reason, please contact Pressco Technical Support.