

# UPGRADING INTELLIMASS SOFTWARE

This upgrade procedure refers to upgrades from 2.X software to a later version of 2.X software.


Upgrading from 1.X to 2.X software requires hardware changes. Please contact Pressco Technical Support if upgrading from version 1.X software.

There are two ways to upgrade Intellimass software. Newer versions of the software have a Software Upgrade function (button) available under the System tab. If your software has this function, upgrade the software from within Intellimass using the first installation method shown. If your software does not have this function, upgrade the software via Windows Explorer using the second method shown.

## CREATE UPGRADE CD

1. Download the upgrade file. If you need site help (registration, finding the download) please contact Pressco Technical Support.
2. Unzip the file to a temporary directory on your PC and burn a CD with all the unzipped files.
  - *Important: Burn the CD with the contents in the CD's root directory.*

## UPGRADE THE SOFTWARE FROM WITHIN INTELLIMASS

1. Log in as Technician or Administrator.
2. Click the Configuration tool button at the top of the screen. 
3. Click the System button in the lower right quadrant. The system will prompt to go offline if it is currently online.
4. Under the System tab, click the Software Upgrade button.
  - *Some older software versions do not have the Software Upgrade button. If that is the case with your system, please see alternate instructions below.*
5. Insert the upgrade media into the Intellimass computer and click Yes when prompted.
6. Follow the instructions on screen.
7. Re-start the system when prompted.

# UPGRADING INTELLIMASS SOFTWARE

## UPGRADE THE SOFTWARE VIA WINDOWS EXPLORER

1. Log in to Intellimass at a high level such as Pressco Technician.
2. Press Control+Alt+Delete.
3. The Windows Security screen should appear with Task Manager as one of the buttons.
  - *That button may be inactive if you aren't logged in to Intellimass at a high enough level.*
4. Select Task Manager.
5. From Task Manager's file menu, select New Task.
6. Choose or type explorer in the Create New Task dialog.
7. Once in Windows Explorer, find Setup.exe on the upgrade media and run it to install INTELLIMASS.
8. Follow on-screen instructions to complete the upgrade.

